

Chapter 17: The Kerberos Configuration File:

krb5.conf

In this chapter we describe the Kerberos configuration file `krb5.conf`.

A `krb5.conf` file must exist in the `/etc` directory on each UNIX node that is running Kerberos. We provide a template for this file in the **krb5conf** product in KITS (under `ftp://ftp.fnal.gov/products/krb5conf/`).

If you install Fermi **kerberos** from KITS using UPS/UPD or RPM for Linux, the **krb5conf** product (and file) gets installed automatically for you. If you obtain Kerberos from another source, you must obtain this file yourself, edit it as necessary, and copy it into the `/etc` directory of your machine.

You may need to update your `krb5.conf` file from time to time as the template in KITS gets updated. New versions are announced on the *kerberos-users@fnal.gov* mailing list.

If you need to change a setting in `krb5.conf` but cannot or don't want to change the file in `/etc`, you can copy `/etc/krb5.conf` to a new file and edit this copy. Then set the environment variable `$KRB5_CONFIG` to the full name of your copy. Your copy will be honored by client programs such as **kinit** or **rlogin**, but not by programs that need a trusted configuration file, e.g., **ksu** and the service daemons.

17.1 What does krb5.conf Control?

The file consists of several stanzas, each of which controls certain aspects of the installation:

- `[libdefaults]` sets defaults for Kerberos on your system, e.g., default realm, default ticket lifetime
- `[realms]` tells where to find the KDCs for each realm
- `[instancemapping]` maps client principal properly (for things like cron jobs which require a special principal)
- `[domain_realm]` maps domains to realms
- `[logging]` tells Kerberos where and how to log errors

- [`appdefaults`] lists default settings for outgoing Kerberized network connection applications and for incoming portal mode connections

In section 17.4 *krb5.conf.template (krb5conf v1_5)* we list the template `krb5.conf` file (current as of November '01) with annotations.

17.2 Reinstall krb5conf Using UPD

To reinstall **krb5conf** and thus update your `/etc/krb5.conf` file using UPS/UPD, log in as *root* (or any login id with permissions to write in `/etc`), and run:

```
% upd install krb5conf -G -c
```

Then on all nodes in the cluster (including the original node), run the command:

```
% ups installAsRoot krb5conf
```

Or instead of the **ups installAsRoot** command, after running **upd install**, you may manually set the `SOURCE_FILE` environmental variable to point to the `krb5.conf.template` script:

```
% SOURCE_FILE=/path/to/krb5/ups/krb5.conf.template
```

and then invoke the `install` script

```
% /path/to/krb5/ups/install
```

17.3 Obtain krb5conf without Using UPD

If you're not running **UPS/UPD**, go to

`ftp://ftp.fnal.gov/products/krb5conf/vx_y/NULL/krb5conf_vx_y_NULL.tar` (where `x_y` is `1_5` as of September 2001).

Download and untar the file. Look at the top of the `installAsRoot` script for instructions on how to install it without **UPS**. If you're not running AFS, check to be sure that the `installAsRoot` script changes the following line in `/etc/krb5.conf` to "false":

```
krb5_run_aklog = false
```

17.4 krb5.conf.template (krb5conf v1_5)

For reference, we provide the `krb5.conf.template` file contents for version `v1_5`, with some explanations inserted. If you install the **krb5conf** product using UPD, the necessary name substitutions will be made as part of the installation; otherwise, you need to edit this file manually.

[libdefaults]

This section sets defaults for Kerberos on your system.

```
ticket_lifetime = 1560
```

There are some implementations of Kerberos that read the above number as seconds, and is equivalent to 26 hours. In MIT-derived code (which Fermi's is), it's read as minutes.

```
default_realm = xMYREALMx
```

The UPD installation process changes `xMYREALMx` to `FNAL.GOV`. (In Kerberos transactions, this `default_realm` is assumed when you mention any principal without its “@REALM” part.)

```
checksum_type = 1
```

```
ccache_type = 2
```

```
default_tgs_etypes = des-cbc-crc
```

```
default_tkt_etypes = des-cbc-crc
```

[realms]

This section lists the realms, and for each the KDCs, admin server (master KDC), the `default_domain` for converting between Kerberos v4 and Kerberos v5 service names, and principal-to-account name matching info.

If and when we cross-authenticate with some other site, each host that wants to initiate connections *to* the other site will have to list that site's realm information here. (We think it won't be necessary for accepting connections *from* that site.)

```
PILOT.FNAL.GOV = {
```

```
    kdc = krb-pilot-1.fnal.gov:88
```

```
    kdc = krb-pilot-3.fnal.gov:88
```

```
    kdc = krb-pilot-4.fnal.gov:88
```

```
    kdc = krb-pilot-5.fnal.gov:88
```

```
    admin_server = krb-pilot-admin.fnal.gov
```

```
    default_domain = fnal.gov
```

```
    auth_to_local = RULE:[1:$1@$0](.*@FNAL\..GOV)s/@.*//
```

This RULE line allows authentication for `username@FNAL.GOV` and `username@PILOT.FNAL.GOV` no matter which is the host's default realm.

```
    auth_to_local = DEFAULT
```

The `auth_to_local` lines provide rules for matching an authenticated principal name to a (local) UNIX name; they are used only if there is no `.k5login` file in the user's UNIX home directory. The value `DEFAULT` is equivalent to having no `auth_to_local`.

```

}
FNAL.GOV = {
    kdc = krb-fnal-1.fnal.gov:88
    kdc = krb-fnal-2.fnal.gov:88
    kdc = krb-fnal-3.fnal.gov:88
    kdc = krb-fnal-4.fnal.gov:88
    kdc = krb-fnal-5.fnal.gov:88
    admin_server = krb-fnal-admin.fnal.gov
    default_domain = fnal.gov
    auth_to_local = RULE:[1:$1@$0](.*@PILOT\.FNAL\.GOV)s/@.*//
    auth_to_local = DEFAULT
}
WIN.FNAL.GOV = {
    kdc = newpckits.fnal.gov:88
    admin_server = newpckits.fnal.gov
    default_domain = fnal.gov
}

```

[instancemapping]

This deals with the instance portion of a principal (see *principal* in the *Glossary*). The lines that follow instruct Kerberos to strip a trailing `/cron/*` or `/cms/*` portion of the client principal when generating a Kerberos v4 ticket for the service called `afs`.

```

afs = {
    cron/* = ""
    cms/* = ""
}

```

[domain_realm]

In this section the domains get mapped to the realms. (This determines the realm in which you need to get a service ticket to log into a Kerberized host in a particular domain.) For individual machines in a domain that need to be mapped to a different realm than the domain as a whole, list each machine separately, mapped to the correct realm. Make your changes in the lower part of this section as noted below.

```

.fnal.gov = PILOT.FNAL.GOV
.minos-soudan.org = FNAL.GOV
xMYNODEx = xMYREALMx

```

The first and third items above are not needed if you use DNS.

```

fsus01.fnal.gov = xMYREALMx
fsus03.fnal.gov = xMYREALMx

```

```
fsus04.fnal.gov = xMYREALMx
```

The previous three are individual AFS server nodes that happen not to have Kerberos V5 at all (yet). To make **aklog** work without spurious error messages, it has to believe that the AFS servers are in the same realm as the host itself.

```
c243580-a.wheaton1.il.home.com = FNAL.GOV
```

```
# The whole "top half" is replaced during "ups installAsRoot
krb5conf", so:
```

```
# It would probably be a bad idea to change anything on or above
this line
```

```
# If you need to add any .domains or hosts, put them here
```

```
[domain_realm]
```

```
.ts.infn.it = PILOT.FNAL.GOV
```

```
.pi.infn.it = PILOT.FNAL.GOV
```

```
.physics.lsa.umich.edu = PILOT.FNAL.GOV
```

```
.phys.ttu.edu = PILOT.FNAL.GOV
```

```
mojo.lunet.edu = FNAL.GOV
```

```
[logging]
```

This section tells Kerberos where and how to log errors; through syslog or directly to file.

```
default = SYSLOG:ERR:AUTH
```

```
[appdefaults]
```

This section lists default application settings (ticket attributes, login parameters, etc.). All of these defaults (or nearly all) can be overridden by a command-line flag. The `krb5.conf` file just sets the defaults for the host. The ftp client does not look for defaults here.

```
default_lifetime = 7d
```

```
retain_ccache = false
```

`retain_ccache` determines whether tickets in a user's ticket cache on a particular host get saved (`true`) or destroyed (`false`) when the user closes his session on that host.

```
autologin = true
```

```
forward = false
```

`forward` should in most cases be set to `true`, in order to forward tickets obtained as "forwardable" to remote hosts by default.

```
renewable = true
```

```
encrypt = true
```

```
krb5_aklog_path = /usr/krb5/bin/aklog
```

The initial list is for common settings. These values are used by all the applications except when an overriding value is listed for a particular application; see below.

```
telnet = {  
}
```

Telnet uses the common settings; no overrides.

```
rcp = {  
    forward = false  
    encrypt = false  
    allow_fallback = true  
}
```

Whereas rcp sets two overrides (the first of which is unnecessary) and one additional parameter.

```
rsh = {  
    allow_fallback = true  
}  
rlogin = {  
    allow_fallback = false  
}  
  
login = {  
    forwardable = true  
    krb5_run_aklog = true  
    krb5_get_tickets = true  
    krb4_get_tickets = false  
    krb4_convert = false  
}
```

`login` is invoked by `telnetd` (not `telnet`) and `sshd` (not `ssh`), and may be invoked by the OS for a local (console) login. CRYPTOCARD logins use these settings.

```
kinit = {  
    forwardable = true  
    krb5_run_aklog = true  
}  
  
pam = {  
    forwardable = true  
}  
  
rshd = {  
    krb5_run_aklog = true  
}  
  
ftpd = {
```

```
krb5_run_aklog = true
default_lifetime = 6h
```

The ticket lifetime here is only invoked for CRYPTOCARD FTP access.

```
}
```

